



MageConnector module documentation. Guide to installation and usage.

This guide is ment for people, familiar with Magento Connect Manager.
If you have any problems during installation process, please report errors at info@bintime.com.

IMPORTANT!

Before installing MageConnector make sure that there are product attributes that will contain Manufacturer Product Number and Manufacturer name.

Products which doesn't contain specified data cannot be correctly displayed.

Please notice also that Manufacturer should be written exactly the same way as it is written on ICEcat (e.g. HP and Hewlett Packard won't be recognized as the same manufacturers)

Step 1. Configuring MageConnector Module

After MageConnector is installed, go to:

admin->System->Configuration->Catalog->ICEcat

Normally such ICEcat module is seen under the path above.

A screenshot of the 'Ice Cat' configuration form in the Magento admin panel. The form has a title bar 'Ice Cat' and a close button. It contains five fields: 'Ice Cat user login' (text input), 'Ice Cat Password' (password input), 'Language' (dropdown menu with 'English' selected), 'Sku Field' (dropdown menu with 'sku' selected), and 'Manufacturer Field' (dropdown menu with 'manufacturer' selected).

If «Access denied» message is displayed, please relogin to admin page.

Fill in login and password to ICEcat. You can get your login in 5 minutes at the website
<http://www.icecat.biz>


Select language that should be used for product descriptions from the dropdown.

Select field of product which contains product code (Manufacturer Product Number)

Select field of product which contains manufacturer name

After this, the Config should be saved.

Now if products contain correct data (MPN, Manufacturer), the datasheet should be displayed, similar to the one below:



If some data is missing, there will be no ICEcat data displayed:

You might have already noticed that category page contains no images for products. Please don't worry as we have taken care of it.

If the web-store is connected to the system Cron (or other task scheduler), images will be downloaded daily at 3.00 AM.

To setup the cron correctly, please make changes in module.

Go to

%your_magento_folder%/app/code/local/Bintime/Icecatimport/etc/config.xml

Find there the following lines:

```
<crontab>
  <jobs>
    <icecatimport>
      <schedule><cron_expr>0 3 * * *</cron_expr></schedule>
      <run><model>icecatimport/observer::load</model></run>
    </icecatimport>
  </jobs>
</crontab>
```

In : <cron_expr>0 3 * * *</cron_expr>.

Set to <cron_expr>* * * * *</cron_expr>.

After this, please run the Cron job.

Just enter the following url in the browser:

http://www.bInTime.com
MageConnector

Date: 2009-11-13



http://%YOUR_DOMAIN_NAME%/cron.php

The update process will take some time, depending on your hardware and Internet channel bandwidth.

When update process (loading of the page) is over, you should see images provided by ICEcat.